

Summary - Complex Mixer

| | |
|-------------------|---|
| Name | complex_mixer |
| Worker Type | Application |
| Version | v1.4 |
| Release Date | September 2018 |
| Component Library | ocpi.assets.dsp_comps |
| Workers | complex_mixer.hdl complex_mixer.rcc |
| Tested Platforms | xsim, isim, modelsim, alst4, ml605, ZedBoard(PL), Matchstiq-Z1(PL), |

Functionality

The Complex Mixer consists of a Numerically Controlled Oscillator (NCO) and a complex multiplier. Complex IQ data is received on the input port and is multiplied with the output of the NCO and put on the output port.

Worker Implementation Details

complex_mixer.hdl

Figure 1 diagrams the complex mixer.




Figure 1: Complex Mixer Functional Diagram

Build time parameters can be used to control the width of the NCO data output, the width of the input data, and the number of stages in the Coordinate Rotation Digital Computer (CORDIC) used to implement the NCO. Additionally, there is a parameter to control insertion of a peak detection circuit.

An **enable** input is available to either enable (true) or bypass (false) the circuit. In bypass mode, pipe-lining registers are not used. FPGA multipliers are used to process input data at the full clock rate. This worker will produce valid output two clock cycles after each valid input.

complex_mixer.rcc

The RCC worker leverages liquid-dsp v1.2 and its *nco* class to generate the internal NCO used in the algorithm. OpenCPI provides RPMs for installing liquid-dsp, which must be installed in order to build and run this worker. More information on this liquid-dsp module can be seen in the online documentation: liquid-dsp.

In the RCC version of this component the samples are converted from fixed point to floating point numbers in order to do that math on a GPP. This conversion introduces a small amount of error in the output data and should

be accounted for when it is used in an application. The conversion equations are as follows:

$$iq_float = \frac{iq_fixed}{2^{15} - 1} \quad (1)$$

$$iq_fixed = iq_float * (2^{15} - 1) \quad (2)$$

In the RCC worker a conversion needs to be done for the phase increment to adhere to the way the HDL phase increment is implemented. The conversion was done in the RCC version of this component because the division operation is very resource intensive in HDL. The conversion from the component property to the liquid-dsp interface input property is as follows:

$$liquid_phs_inc = phs_inc * \frac{2\pi}{0x7FFF * 2} \quad (3)$$

Theory

The Complex Mixer worker inputs complex signed samples and performs a complex multiply with a digital sine wave produced by an numerically controlled oscillator (NCO). The resulting output data is a frequency shifted version of the input data.

The magnitude of the frequency shift is determined by the output frequency of the NCO, which can be calculated with the following equation:

$$nco_output_freq = sample_freq * \frac{phs_inc}{2^{phs_acc_width}} \quad (4)$$

In this component, **phs_inc** is runtime configurable and has a data type of 16 bit signed short. **phs_acc_width** is fixed at 16. The input clock frequency is the sample rate of the samples. The amplitude of the NCO's sine wave is also runtime configurable via the **mag** property. Note that the **mag** property value should only ever be set to a value within the following range in order for the worker to operate properly.

$$-2^{(NCO_DATA_WIDTH-p-1)} \leq mag \leq 2^{(NCO_DATA_WIDTH-p-1)} - 1 \quad (5)$$

A positive and negative **phs_inc** will mix up and down, respectively. The following equation can be used as an aid for setting the **phs_inc** to have the desired mixing affect.

$$x_{out}[n] = x_{in}[n] * \frac{mag}{2^{NCO_DATA_WIDTH-p-1}} * e^{(j2\pi(sample_freq * \frac{phs_inc * n}{2^{phs_acc_width}}) + phs_init)} \quad \forall n, n \geq 0 \quad (6)$$

Block Diagrams

Top level




Figure 2: Complex Mixer Top Level Block Diagram

State Machine

Only one finite-state machine (FSM) is implemented by this worker. The FSM supports Zero-Length Messages.




Figure 3: Zero-Length Message FSM

Note: In future releases this finite-state machine will be replaced with a register-delay based mechanism, currently exemplified in the dc offset filter

Source Dependencies

complex_mixer.rcc

- ocpi-prereq-liquid-1.2.0-*.rpm and ocpi-prereq-liquid-platform-zynq-1.2.0-*.rpm need to be installed in order to build and run this worker.

/opt/opencpi/prerequisites/liquid/include/liquid/liquid.h

complex_mixer.hdl

- projects/assets/components/dsp_comps/complex_mixer.hdl/complex_mixer.vhd
- projects/assets/hdl/primitives/dsp_prims/dsp_prims_pkg.vhd
 - projects/assets/hdl/primitives/dsp_prims/nco/src/nco.vhd
 - projects/assets/hdl/primitives/dsp_prims/cordic/src/cordic_pr.vhd
 - projects/assets/hdl/primitives/dsp_prims/cordic/src/cordic.vhd
 - projects/assets/hdl/primitives/dsp_prims/cordic/src/cordic_stage.vhd
- projects/assets/hdl/primitives/util_prims/util_prims_pkg.vhd
 - projects/assets/hdl/primitives/util_prims/mult/src/complex_mult.vhd
 - projects/assets/hdl/primitives/util_prims/pd/src/peakDetect.vhd
- projects/assets/hdl/primitives/misc_prims/misc_prims_pkg.vhd
 - projects/assets/hdl/primitives/misc_prims/round_conv/src/round_conv.vhd

Component Spec Properties

| Name | Type | SequenceLength | ArrayDimensions | Accessibility | Valid Range | Default | Usage |
|---------|-------|----------------|-----------------|--------------------|-------------|---------|-------------------------------------|
| enable | Bool | - | - | Readable, Writable | Standard | true | Enable(true) or bypass(false) mixer |
| phs_inc | Short | - | - | Readable, Writable | * | -8192 | Phase increment of NCO |

Worker Properties

complex_mixer.hdl

| Type | Name | Type | SequenceLength | ArrayDimensions | Accessibility | Valid Range | Default | Usage |
|----------|--------------------|--------|----------------|-----------------|---------------------|-------------|---------|--|
| Property | CHIPSCOPE_p | Bool | - | - | Readable, Parameter | Standard | false | Include Chipscope circuit |
| Property | NCO_DATA_WIDTH_p | UChar | - | - | Readable, Parameter | 12/16 | 12 | Output data width of NCO |
| Property | INPUT_DATA_WIDTH_p | UChar | - | - | Readable, Parameter | 12/16 | 12 | Input port data width |
| Property | CORDIC_STAGES_p | UChar | - | - | Readable, Parameter | 16 | 16 | Number of CORDIC stages implemented in NCO |
| Property | PEAK_MONITOR_p | Bool | - | - | Readable, Parameter | Standard | true | Include peak monitor circuit |
| Property | peak | Short | - | - | Volatile | Standard | - | Output of peak detector |
| Property | phs_init | UShort | - | - | Readable, Writable | 0 | 0 | Initial phase of NCO |
| Property | mag | UShort | - | - | Readable, Writable | * | 1024 | Magnitude of NCO output, which must be in the range $[-2^{(NCO_DATA_WIDTH_p-1)} \quad 2^{(NCO_DATA_WIDTH_p-1)}-1]$ in order for the worker to operate properly. |
| Property | messageSize | UShort | - | - | Readable, Writable | 8192 | 8192 | Number of bytes in output message |
| Property | data_select | Bool | - | - | Readable, Writable | Standard | false | In Bypass Mode: selects data to output: 0=input data, 1=output of NCO |

Component Ports

| Name | Producer | Protocol | Optional | Advanced | Usage |
|------|----------|-------------------|----------|----------|------------------------|
| in | false | iqstream_protocol | false | - | Signed complex samples |
| out | true | iqstream_protocol | false | - | Signed complex samples |

Worker Interfaces

complex_mixer.hdl

| Type | Name | DataWidth | Advanced | Usage |
|-----------------|------|-----------|-------------------------|------------------------|
| StreamInterface | in | 32 | ZeroLengthMessages=true | Signed Complex Samples |
| Type | Name | DataWidth | Advanced | Usage |
| StreamInterface | out | 32 | ZeroLengthMessages=true | Signed Complex Samples |

Control Timing and Signals

The Complex Mixer HDL worker uses the clock from the Control Plane and standard Control Plane signals.

There is a startup delay for this worker. Once the input is ready and valid and the output is ready, there is a delay of `CORDIC_STAGES_p+3` before the first sample is taken. After this initial delay, valid output data is given 2 clock cycles after input data is taken.

| Latency |
|----------------|
| 2 clock cycles |

Worker Configuration Parameters

complex_mixer.hdl

Table 1: Table of Worker Configurations for worker: complex_mixer

| Configuration | NCO_DATA_WIDTH_p | PEAK_MONITOR_p | ocpi_debug | CHIPSCOPE_p | INPUT_DATA_WIDTH_p | ocpi_endian | VIVADO_ILA_p | CORDIC_STAGES_p |
|---------------|------------------|----------------|------------|-------------|--------------------|-------------|--------------|-----------------|
| 0 | 12 | true | false | false | 12 | little | false | 16 |
| 1 | 16 | true | false | false | 16 | little | false | 16 |
| 2 | 12 | true | false | false | 12 | little | true | 16 |

Performance and Resource Utilization

Table 2: Resource Utilization Table for worker: complex_mixer

| Configuration | OCPI Target | Tool | Version | Device | Registers (Typ) | LUTs (Typ) | Fmax (MHz) (Typ) | Memory/Special Functions |
|---------------|-------------|---------|---------|------------------|-----------------|------------|------------------|--------------------------|
| 0 | zynq | Vivado | 2017.1 | xc7z020clg484-1 | 1214 | 2555 | N/A | DSP48E1: 6 |
| 0 | virtex6 | ISE | 14.7 | 6vlx240tff1156-1 | 1215 | 2816 | 222.207 | DSP48E1: 6 |
| 0 | stratix4 | Quartus | 17.1.0 | EP4SGX230KF40C2 | 1268 | 1742 | N/A | DSP18: 8 |
| 1 | zynq | Vivado | 2017.1 | xc7z020clg484-1 | 1452 | 3084 | N/A | DSP48E1: 6 |
| 1 | virtex6 | ISE | 14.7 | 6vlx240tff1156-1 | 1407 | 3319 | 165.044 | DSP48E1: 8 |
| 1 | stratix4 | Quartus | 17.1.0 | EP4SGX230KF40C2 | 1468 | 1926 | N/A | DSP18: 12 |
| 2 | zynq | Vivado | 2017.1 | xc7z020clg484-1 | 1216 | 2566 | N/A | DSP48E1: 6 |
| 2 | virtex6 | ISE | 14.7 | 6vlx240tff1156-1 | 1216 | 2820 | 222.207 | DSP48E1: 6 |
| 2 | stratix4 | Quartus | 17.1.0 | EP4SGX230KF40C2 | 1268 | 1742 | N/A | DSP18: 8 |

Test and Verification

Test cases are derived from the number of properties, and their respective values, as listed in the `complex_mixer-test.xml`. Specifically, the `complex_mixer.rcc` and `complex_mixer.hdl` implementations tested, as follows:

- 1) Bypass (RCC & HDL): The input data is forwarded to the output port. For verification of this case, the output file is byte-wise compared to the input file.
- 2) Normal mode (RCC & HDL): The NCO is configured to tune the input signal to baseband. For verification, an FFT of the output data is performed and the max value of the FFT is checked to be at DC (0 Hz).

For all cases, the input file contains a tone of 12.5 Hz sampled at 100 Hz and an amplitude of 32767.